



# S4B SERVER PRESENCE

Version 2.0.49

PREREQUISITES AND INSTALLATION GUIDE

A large, 3D geometric graphic composed of several overlapping, semi-transparent blue and grey rectangular blocks, creating a complex, layered structure.

April 2018

## **Copyright and Disclaimer**

This document, as well as the software described in it, is furnished under license of the Instant Technologies Software Evaluation Agreement and may be used or copied only in accordance with the terms of such license. The content of this document is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Instant Technologies. Instant Technologies assumes no responsibility or liability for any errors or inaccuracies that may appear in this document. All information in this document is confidential and proprietary.

Except as permitted by the Software Evaluation Agreement, no part of this document may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Instant Technologies .

Copyright © 2005 - 2014 Instant Technologies, All rights reserved.

## **Trademarks**

All other trademarks are the property of their respective owners.

## **Contact Information**

See our Web site for Customer Support information.

<http://www.instant-tech.com/>



ISV/Software Solutions

## CONTENTS

Introduction.....	3
Prerequisites .....	3
Installation .....	3

## INTRODUCTION

This guide is designed to show prerequisites and how to install S4B Server Presence.


If you have any questions during this process, please contact [support@instant-tech.com](mailto:support@instant-tech.com).

## PREREQUISITES


- 64-bit computer.
- Windows Server 2008 R2 SP1, Windows Server 2012 and 2016.
- Unified Communications Managed (UCMA) API 4.0 Runtime.

## INSTALLATION


- 1) Download S4B Server Presence installer.
- 2) Unzip the file and open PresenceService2Setup.exe.

A small icon representing the file PresenceService2Setup.exe, showing a blue folder icon with a white document icon inside.


- 3) Click **Next** on the installer Welcome page.



- 4) Click **Next** on the installer Installation Folder page.



- 5) Click **Install** on the installer Ready to Install page.



- 6) After installation is completed, you will see the Configure Web Presence Service window. Fill the Configuration form.

- a) Lync Server Address:
  - The URL or address to your Lync server. For example, mylyncserver.instant-tech.com.
- b) Presence Lookup Account SIP:
  - Use one of the sip from your Lync server. For example, sip:myaccount@instant-tech.com
- c) Presence Lookup Account Domain:
  - The account domain from your account sip, sip:myaccount@instant-tech.com. For example, instant-tech.com
- d) Presence Lookup Account Username:
  - The account username located in your sip, sip:myaccount@instant-tech.com. For example, myaccount.
- e) Presence Lookup Account Password:
  - The sip password in your Lync server.

Configure Web Presence Service

Lync Server Address:  
mylyncserver.instant-tech.com

Presence Lookup Account SIP:  
sip:myaccount@instant-tech.com

Presence Lookup Account Domain:  
instant-tech.com

Presence Lookup Account Username:  
myaccount

Presence Lookup Account Password:  
.....

Close Test Save

Start Service

- 7) Once the form is filled out, click **Test**, then click **Save**.
- 8) Finally, click **Start Service**.
- 9) Now, open a web browser and go to **[servername]/WebPresence** to check Documentation.